


Cara Setting Email Client di Thunderbird

-Thunderbird-

<p>Set Up Your Existing Email Address</p> <p>To use your current email address fill in your credentials. Thunderbird will automatically search for a working and recommended server configuration.</p> <p>Your full name <input type="text" value="abiga ulihta"/></p> <p>Email address <input type="text" value="abiga.ulihta@cbn.net.id"/></p> <p>Password <input type="password" value="....."/></p> <p><input checked="" type="checkbox"/> Remember password</p> <p>Configure manually <input type="button" value="Cancel"/> <input type="button" value="Continue"/></p> <p>Your credentials will only be stored locally on your computer.</p> 	<p>Keterangan :</p> <ol style="list-style-type: none">1. Your full name Masukkan nama lengkap anda ke kolom tersebut2. Email address Masukkan akun Email Enterprise anda ke kolom tersebut3. Password Masukkan kata sandi dari akun Email Enterprise anda4. Configure manually Klik tombol 'Configure manually' untuk melakukan konfigurasi email secara manual
--	--

Manual configuration

INCOMING SERVER

1

Protocol: IMAP

Hostname: c6.icoremail.net

Port: 993

Connection security: SSL/TLS

Authentication method: Normal password

Username: abiga.ulihta@cbn.net.id

OUTGOING SERVER

2

Hostname: c6.icoremail.net

Port: 465

Connection security: SSL/TLS

Authentication method: Normal password

Username: abiga.ulihta@cbn.net.id

[Advanced config](#)

Re-test

3

Cancel

Done

Thunderbird will attempt to auto-detect fields that are left blank.

Keterangan :

- 1. Incoming Server**
Protocol: IMAP/POP3
Hostname: c6.icoremail.net
Port: 993 (IMAP) / 995 (POP3)
Connection Security: SSL/TLS
Authentication Method: Normal Password
Username: isi alamat email
- 2. Outgoing Server**
Hostname: c6.icoremail.net
Port: 465
Connection Security: SSL/TLS
Authentication Method: Normal Password
Username: isi alamat email
- 3. Re-test**
Untuk melakukan pengetesan koneksi pada konfigurasi yang sudah dimasukkan sebelumnya
- 4. Done**
Untuk login ke Thunderbird

Note: Untuk **Port SMTP 587** tidak dibuka dengan pertimbangan keamanan