


## Panduan email CBN di Xiaomi



### *CBN email setup in Xiaomi*

*Has been tested using Xiaomi Redmi 2 Prime*

1. Pilih **Settings – Add.**  
*Choose Settings – Add.*



2. Pilih **Personal (POP3)** dan isi alamat email dan password lalu **Next**.  
*Choose **Personal (POP3)** and fill email address and password then **Next**.*



3. Isi dengan informasi dibawah ini lalu klik **Next**.

*Fill with information below then click **Next**.*


**Username : your email address**

**Password : your email password**

**Server : secure.emailsrvr.com**

**Port : 995**

**Security type : SSL/TLS**



6:23 265K/s XL 4G 54%

### Incoming server settings

USERNAME  
email@domain.com

PASSWORD  
.....  
 Show password

SERVER  
secure.emailsrvr.com

PORT  
995

SECURITY TYPE  
SSL/TLS

Delete email from server  
When I delete from Inbox

< NEXT >

CBN

**SMTP Server : *secure.emailsrvr.com***


**Port : *465***

**Security type : *SSL/TLS***

**Checklist *Require signin***

**Username : *your email address***

**Password : *your email password***



6:24 0.71K/s XL 4G 54%

### Outgoing server settings

SMTP SERVER  
secure.emailsrvr.com

PORT  
465

SECURITY TYPE  
SSL/TLS

Require signin

USERNAME  
email@domain.com

AUTHENTICATION  
Password ..... X

Show password

< NEXT > CBN


5. Ceklist pilihan di **Account options** berikut lalu **Next**.  
Isi rentang waktu kapan email akan didownload di **Sync frequency**.  
Ceklist **Notify me when email arrives** jika ingin ada pemberitahuan ketika email masuk.  
Ceklist **Sync email from this account** jika ingin sinkron otomatis dari server email.

*Checklist option in **Account options** below then **Next**.*

*Fill span of time when the email will be downloaded in **Sync frequency**.*

*Checklist **Notify me when email arrives** if you want a notification when there is incoming email.*


*Checklist **Sync email from this account** if you want to sync automatically from email server.*



6. Isi dengan informasi berikut lalu **Next**.  
*Fill with information below then Next.*

**Account name (optional) : your account name**

**Your name : your display name**



6:25 0.04K/s XL 4G 54%

Your account is set up  
and email is on its way!

Account name (optional)  
email@domain.com

Your name  
Your Name / Nama Anda  
Displayed on sent messages

NEXT >

CBN